

Requirements:



Note: This is only a full MainSystem Software update via USB drive

- USB stick with at least 2 GB memory.
- A Windows based PC or notebook to prepare the USB.

Note: The USB stick must be formatted to FAT32 before use (right-click on the USB drive in the Win Explorer → choose "Format" → select FAT 32 → start).

The ZENEC Z-E3756 E>GO device will restart several times during the software update and remain off for a few seconds (black screen for approx. 10 ~ 15 sec.), before the device reboots, since a software image is created.

Installation of MainSystem Software Update via USB drive:

1. Download the software update package „swupdate_6529B_20181031.zip“. Please don't unzip the update file.
2. Copy the zip update file to the root directory of your USB stick.
3. Connect the USB stick to your naviceiver.
4. Enter the naviceiver setup. Tap on [Setup] → [System] → [Software Update] → [GREEN CHECK] 
5. The naviceiver will unzip the update file and starts the update process automatically.
6. Your ZENEC system will be updated in a step-by-step process. The complete update procedure takes approx. 2~3 minutes. A status bar shows the update progress.
7. Remove the USB stick, if the update process has completed successfully. Note: The installation process successfully done, if unit stay in Tuner page.
8. Enter the naviceiver setup and load the factory defaults. Tap on [Setup] → [System] → [Load Factory] → [GREEN CHECK] 
9. Please do a versions check.


Version checking:

After completion of the software update, version checking is crucial to validate full success. If the installed software version differs with listed versions below, a full re-installation of the entire software update is required.


Review of device software version:

To check the Main Software Version, enter the naviceiver setup. Tap on [Setup] → [System] → see the Software Version Info line.

Version: **v1.4.9**
(Software Version Info)



Notes:

- Do not operate or turn off while device is performing a software update.
- After completion of the software update always load the factory defaults.
[Setup] → [System] → [Load Factory] → [GREEN CHECK] 
- After the factory settings have been loaded, the camera grid-lines must be set again (see chapter "CAMERA GRID-LINES" in the Device User Manual).

Important:

To initialize the TMC function on the ZENEC Z-E3756 E>GO device, the following software components need to be updated:

1. Download and installation of the MainSystem software (as of version v1.4.9) on the device.
2. Download and installation of the navigation software 9.35.2.129824 Oct 13 2018 from Naviextras, with a roll-out date starting from October 13, 2018 (contains new navigation engine).

iGO navigation version:



The MainSystem software can be found on the ZENEC homepage under "Support" → "Software Updates" → "FIAT" → "Z-E3756".

The actual navigation software update can be downloaded with the PC or notebook from the Naviextras Internet portal <https://zenec.naviextras.com/shop/portal/newLogin>